## Multi-Channel Encoding Monitor (MCEM)

## **MCEM Email Activation Steps**

The MCEM can be configured to send an email to the user when the unit is alerting or alarming. To set up email alerting via the web interface please complete the following steps:

- 1. Verify the computer is connected to your LAN and the MCEM via the rear panel ethernet port.
- 2. Identify the MCEM's IP address. This can be found via the front panel LCD display. From the front panel, press the top arrow 3 times.
- 3. Open a web browser (Microsoft Internet Explorer<sup>®</sup>, Firefox<sup>®</sup>, Chrome<sup>™</sup>, Opera<sup>®</sup>, or Safari<sup>®</sup>) on the computer connected to the monitor and enter the following in the address window: https://IP-address
- 4. The login window will open. Enter the user name, **Station** (case-sensitive), and the password, **Columb1aMD** (case-sensitive), and click the OK button.
- 5. Navigate to the menu item email configuration.
- 6. Enter the recipient's email address.
- 7. Check the box for Activate Email Notification.
- 8. If "Use MCEM Email Server" is checked, clear the checkbox.
- 9. Enter the URL and port for the email server.
- 10. Enter the sender's email address and password (login credentials). Note: the password is encrypted and masked. To see the password before it is saved, check the "Show Checkbox."
- 11. Enable TLS and TLS Start unless these are not supported.
- 12. Click "Save."
- 13. Click "Test." A notification appears that the test email is about to be sent. This can take up to 2 minutes. A message will appear that indicates whether the email was sent. If it was not sent, see Appendix D of MCEM manual to troubleshoot the issue.

			Your ENC Monitor L50	Station Log Ou
				Menu
Aonitor Information				
Entities		-FM   ChPairB   ChPairC   ChPairD		
mail Configuration				
Activate Email Notificati	on ?			
Use MCEM Email Server ?			10	
Server Online Check				
Email Server URL				
Email Server Port				
Sender's Email Account		example@nielsen.com		
Sender's Email Account Password		Password		
Use TLS ?				
Use TLS Start ?				
Email Address that Receives Alarms		example2@nielsen.com		

For more information contact your Audio Client Engineer at 1-866-767-7212, or email encoding@nielsen.com

Copyright © 2021 The Nielsen Company (US), LLC. All Rights Reserved.

